

一、安装部分

更新源

yum -y update

1、安装组件

```
yum -y install git wget curl zip unzip screen;wget  
"https://raw.githubusercontent.com/qinghuas/ss-panel-and-ss-py-mu/master/ssr.sh";bash  
ssr.sh
```

```
apt-get -y install git wget curl zip unzip screen;wget  
"https://raw.githubusercontent.com/qinghuas/ss-panel-and-ss-py-mu/master/ssr.sh";bash  
ssr.sh
```

选择安装 BBR、Aria2、fail2ban、Server Status

Aria2 需要修改参数（密钥及储存位置/home）

宝塔

```
yum install -y wget && wget -O install.sh http://download.bt.cn/install/install.sh && sh  
install.sh
```

或 `wget -O install.sh http://download.bt.cn/install/install-ubuntu.sh && sudo bash install.sh`

宝塔需修改端口为 8880 及密码

2、安装 FileManager

```
cd /root
```

```
wget https://github.com/filebrowser/filebrowser/releases/download/v1.5.5/linux-amd64-  
filebrowser.tar.gz
```

```
tar -zxvf linux-amd64-filebrowser.tar.gz
```

版本号可修改

3、运行 FileManager 及安装 screen

```
yum -y install screen
```

启动 FileManager

```
screen -dmS filemanager ./filebrowser --port 23333 --scope /home
```

（停止 screen -r filemanager）

4、下载 AriaNg

<https://github.com/mayswind/AriaNg/releases/download/0.4.0/aria-ng-0.4.0.zip>

解压到网站目录

二、调试

1、用宝塔建站，适当选择反代。

2、宝塔开放端口

三、Goflyway 安装与 CDN

1、安装 Goflyway

```
wget -N --no-check-certificate https://softs.fun/Bash/goflyway.sh && chmod +x  
goflyway.sh && bash goflyway.sh
```

备用

```
wget -N --no-check-certificate
```

```
https://raw.githubusercontent.com/ToyoDAdoubi/doubi/master/goflyway.sh &&  
chmod +x goflyway.sh && bash goflyway.sh
```

2、转发 (先 kill)

```
cd /usr/local/goflyway
```

```
kill -9 $(ps -ef|grep "goflyway"|grep -v grep|awk '{print $2}')
```

```
nohup ./goflyway -k="hsb1997Z" -l=":8080" -proxy-  
pass="http://kernel.ubuntu.com/~kernel-ppa/mainline/" > /tmp/goflyway.log  
2>&1 &
```

重启后需运行

```
screen -dmS filemanager ./filebrowser --port 23333 --scope /home
```

```
cd /usr/local/goflyway
```

```
kill -9 $(ps -ef|grep "goflyway"|grep -v grep|awk '{print $2}')
```

```
nohup ./goflyway -k="hsb1997Z" -l=":8080" -proxy-  
pass="http://kernel.ubuntu.com/~kernel-ppa/mainline/" > /tmp/goflyway.log  
2>&1 &
```

附录：端口列表（原始端口）

Goflyway 8080

宝塔控制面板 8880

Aria2 控制面板 (AriaNG) 80

网盘服务 23333

SSR 管理脚本安装

```
wget -N --no-check-certificate
```

```
https://raw.githubusercontent.com/ToyoDAdoubi/doubi/master/ssrmu.sh &&
```

```
chmod +x ssrmu.sh && bash ssrmu.sh
```

锐速

```
wget --no-check-certificate -O rskernel.sh
```

```
https://raw.githubusercontent.com/uxh/rskernel/master/rskernel.sh && bash
```

```
rskernel.sh
```

```
yum install net-tools -y && wget --no-check-certificate -O appex.sh
```

```
https://raw.githubusercontent.com/0oVicero0/serverSpeeder_Install/master/appe
```

```
x.sh && chmod +x appex.sh && bash appex.sh install
```

网站 <https://www.vultrcn.com/7.html>

v2

```
bash <(curl -s -L https://233blog.com/v2ray.sh)
```

配置

```
vi /etc/v2ray/config.json
```

```
5356631d-321b-416f-b463-fe84f67e14f3
```

与宝塔安装时先安 v2 后运行

```
systemctl unmask firewalld.service
```

转发

```
wget -N --no-check-certificate
```

```
https://raw.githubusercontent.com/ToyoDAdoubi/doubi/master/haproxy.sh &&
```

```
chmod +x haproxy.sh && bash haproxy.sh
```